# **DCR** (Distributed Communication Router)

# **DCR to Site Controller Protocol**

Version 1.3d 10 April 2014



This document is the property of Teosis A.S. It is not to be used or duplicated without written permission of the owner, and is not to be used in any way inconsistent with the purpose for which it is loaned. Teosis A.S. shall not be liable for technical or editorial errors or omissions which may appear in this document. It also retains the right to make changes to this specification at any time without prior notice.

**Table of contents** 



## Summary of changes

Changes resulting in document revisions will be summarized in this table in reverse chronological sequence. Revision numbers and letters will highlight the text changed in new document versions.

Date	Version	Modified By	Modifications
15 June 2004	1.00a	M.Yaşar Orhon	First Release
26 November 2006	1.01d	u	Added Transaction CD151 (ECR Plate)
08 October 2009	1.02b	u	Added CD152 (Loyalty Info to ECR command).
10 February 2010	1.02c	и	Added CD153 (Slip Data to ECR command).
01 April 2010	1.02e	u	Revized CD152, removed CD152

## **Acronym Table**

The following table contains a list of acronyms used in this document.

Acronym	Definition					
DCR	Distributed Communication Router					
ECR	Electronic Cash Register					
CRC	Cyclic Redundancy Check					
PIN	Personal Identification Number					
PPU	Price Per Unit					
STP	Submerged Turbine Pump					
FP	Filling Point (a set of one or more hoses, of which only one can be active at any time)					
VID	Vehicle Identification Device (*TTS)					
CID	Customer Identification Device (*MTS)					
MPD	Multi Product Dispenser (a single physical device which may contain one ore more fueling points)					
MPP	Multi Product Pump					
LCD	Liquid Crystal Display					
IFS	Intelligent Fueling Systems					
SCU	Site Controller Unit					
CL	Current Loop					
MCU	Micro Controller Unit					



#### **General descriptions**

The standard data link is based on a master/slave relationship, where the master polls the slaves. If the master wants to send data to a slave, it sends a block with data instead of a poll. If the slave wants to send data it answers with data on a poll. Half duplex is used.

The protocol is code transparent and byte oriented. The protocol required for DCR implementation shall provide for variable length messages.

#### **Data format**

Data transfer	Asynchronous
Bit rate	9600 / 19200 bits per socond
Data bits	8
Stop bits	1
Parity	Odd

#### Note:

A MARK corresponds to loop current "ON" (45mA), a SPACE corresponds to loop current "OFF" (0 mA). S4S protocol shall not be baud-rate dependent. A baud rate of 19200 shall be possible, alternatively 9600, if distance and type of wiring are restrictive.

#### **Interface requirements**

#### **Explosion proofing:**

As fuel dispensers are located in a hazardous area, mechanical and electrical components of the interface, and its installation and service must satisfy relevant hazardous area equipment standards.

#### **Cable characteristics:**

Current loop cabling should satisfy the following requirements:

Insulation 500 Vdc (min.)

Loop length 400 meters (max.) Loop resistance 10 Ohms (max.)

Input inductance 100 uH (max. at any terminals)
Input capacitance 10 nF (max. at any terminals)

while a separate twisted pair should be regarded as the ideal cabling solution, acceptable performance is usually obtained from non-twisted pairs in the same conduit (or even the same sheath) as pump/dispenser power and control cables.

#### Voltage and Current levels:

Loop current 45 mA +/- 5% Open circuit voltage 40 Vdc +/- 5%

#### Note 1:

The maximum allowable voltage drop across any loop tranceiver (either in a pump/dispenser or a controller) at a loop current of 45mA is 2.0 Volts.

#### Note 2:

While common mode voltages are likely to have little effect on data integrity, common mode voltage levels should be below 50Vdc to minimise personnel and property hazards.

#### **Galvanic isolation**

Galvanic isolation may be required in each unit

#### Data rate

DCR Serial protocol shall not be baud-rate dependent. A baud rate of 19200 shall be possible, alternatively 9600, if distance and type of wiring are restrictive.

#### **Code transparence**

Code transparence for 8 bit data is achieved by Data Link Escape (DLE) insertion. DLE insertion is needed when any data byte or CRC has the value SF(Stop Flag).

Transmitting device transmit DLE before SF is transmitted in the data field. Receiving device check when receiving SF, if previous received character was DLE. If so DLE is over written by the received SF in the line buffer.

Inserted DLE's are not included in the CRC-calculation.

### Reliable data transfer

DCR Serial protocol must provide for reliable data transfer. Error checking to be implemented by CRC16 (CCITT). Parity checking is required on each byte.

#### Operational specifics

DCR Serial protocol shall operate half-duplex and transmit data in asynchronous start-stop format.



### **Buffer size**

Buffer size is aplication dependent. However, maximum is 256 byte including control characters. Different slaves can have different buffer size.

#### Control characters in the protocol

ETX 03h End of TextDLE 10h Data Link EscapeSF FAh Stop Flag


Some abbreviation explanations:

**ADR** Slave device address for message (00h-0FFh).

**CRC-1** LSB of CRC-16 word. CRC is calculated from the first byte in the message (ADR) to the last data byte. CRC is initialized to 0000h.

CRC-2 MSB of CRC-16 word.

CTRL Control character and block sequence number.



Different control characters:

POLL 20h
DATA 30h-3Fh
IAP 40h
NAK 50h-5Fh
EOT 70h-7Fh
ACK C0h-CFh
ACKPOLL E0h-EFh

The master has one independent TX# for each slave. Each slave has one TX#. When data is sent from the master or the slave a new TX# is generated for each new data block. The TX# is then returned from the master or the slave in ACK, NAK, EOT or ACKPOLL. Slave answering EOT at POLL contains 0 in TX#. TX# is initiated to 0 after restart of protocol and then incremented by one for each successfully transmitted data block. TX# wraps around to 1 after Fh.

#### Messages from master to slave

POLL : ADR+CTRL+SF

DATA: ADR+CTRL+DATA1+DATAn+CRC-1+CRC-2+ETX+SF


ACK : ADR+CTRL+SF NAK : ADR+CTRL+SF


### Messages from slave to master

EOT : ADR+CTRL+SF


DATA: ADR+CTRL+DATA1+DATAn+CRC-1+CRC-2+ETX+SF

ACK : ADR+CTRL+SF NAK : ADR+CTRL+SF





### Possible answer alternatives



#### **Error recovery**

Error recovery is done when the expected block sequence number does not match the real one. It is done by both the master and the slave. This is a listing of all different situations when error recovery should be done. The TX#-check should be done in the following sequence.

- 1. TX# = tx Last received TX#. The transmitting unit did not get my last ACK. Skip data and answer ACK. Note that this must be done also when TX# = 0.
- 2. TX# = 0 The transmitting unit has been restarted. Initiate the expected TX# to 0, accept data and send ACK.
- 3. TX# >> tx Expected. If expected TX# = 0 this means that actual unit has been restarted and the expected TX# should be sent to the one just received. If so accept data and send ACK. Otherwise another error has occurred and the block should be answered with NAK.

NAK is sent if TX#-error is found in received data. The slave shall not answer at parity error or CRC-error.

The unit transmitting data has the responsibility to restart the communication procedure when NAK has been received 3 times for identical message.

#### **Timing**


Each unit must be capable to receive characters at 19200 / 9600 baud without delays between characters. The master controls the timing. The slave must respond to a poll or data within 25 ms, i.e. transmit the first character after a complete poll or data. The slave must be capable to receive an ACK and a poll transmitted from the master as one continuous byte stream (two lines 3 bytes). In this case ACK and poll are for two different device addresses. If ACK and poll are for the same device then ACKPOLL is sent as one message (3 bytes).

#### **Hardware**

RS485 / Current-Loop with or without galvanic isolation



## Pump status change diagram



In the following table the possible status changes are listed.

From Status	To Status	Comment
	CALL	Pump nozzle out
IDLE	AUTHORIZED	SCU Authorize command
	ERROR	Pump communication timeout or Pump fatal error detected
	WAIT	Pump nozzle out
AUTHORIZED	IDLE	SCU Unauthorize command or SCU Timeout
	ERROR	Pump Timeout
	AUTHORIZED	Pump nozzle in or Pump Timeout
WAIT	BUSY	ECR Authorize command or ECR Timeout
	ERROR	Pump Timeout
	WAIT	SCU Authorize command or SCU Timeout or SCU Disabled
CALL	IDLE	Pump nozzle in
	ERROR	Pump Timeout
DUCY	UNPAID	Pump nozzle in or Pump Timeout
BUSY	PAUSED	SCU Suspend command
DALICED	BUSY	SCU Resume command
PAUSED	PAID	Pump Timeout or Pump nozzle in
DAID	UNPAID	ECR Paid command or ECR Timeout
PAID	IDLE	SCU Paid command and ECR Paid or ECR Timeout
UNPAID	IDLE	SCU Paid command or SCU Timeout or SCU Disabled
ERROR	IDLE	Error Recovered

#### **General description**

This document describes the communications interface to DCR.

This interface, which employs a current loop or RS485 as the data transmission medium, defines allowed states for DCR, allowed state transitions, and the commands and data that may be transmitted and received by DCR and the Console.

Only The protocol above the line protocol is described. From the line protocol, a device address and a buffer with data are received. All error handling e.g. CRC and parity check is made in the line protocol.

Each DCR has a device address (50h - CFh). A DCR shall handle a block if the block is addressed to the DCR. The test of device address is made in the line protocol.

#### **Protocol levels**

The protocol is divided into 3 levels:


Level 1 Electronic level.

Level 2 Line protocol level.

Level 3 Application level.

Level 2 is handling is polling of devices and transport of blocks that are created by level 3. Level 2 cheks that a block is transmitted correctly. The check is made with CRC, parity and block sequence number. If an error occurs, retransmission is handled by level 2.

At level 3 blocks are transmitted between DCR controller and Console. A block can contain one or more transactions that are specified in this document.



## CD127 Preset Amount / Volume

## Command / Response Syntax :

Valid DCR State :	All
Valid Nozzle State :	IDLE

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	7Fh	1	HEX	Transaction number
LNG	6	1	HEX	Number of data bytes in the transaction
PNZ	n	1	BCD	Pump & Nozzle number
				MSD (Pump number)LSD (Nozzle number)0 = Illegal0 = Any Nozzle1 to n = Pump number1 to n = Nozzle number(Max. 4 pump)(Max 5 nozzle)
PTYP	0~2	1	BCD	Preset type (0=unlimited, 1=Money, 2=Liter)
PVAL	n	4	BCD	Preset value

State after nozzle accepts the command :	None
Response after POLL :	None

## CD128 Request Pump Status

### **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	80h	1	HEX	Transaction number
LNG	1	1	HEX	Number of data bytes in the transaction
PNZ	n	1	BCD	Pump & Nozzle number
				MSD (Pump number) 0 = Illegal 1 to n = Pump number (Max. 4 pump)  LSD (Nozzle number) 0 = MPD 1 to n = Nozzle number (Max 5 nozzle)

State after nozzle accepts the command :	None
Response after POLL :	DC128

# DC128 Pump Status

This transaction is sent by the DCR asynchronously when status changed.

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	80h	1	HEX	Transaction number
LNG	2 or 6	1	HEX	Number of data bytes in the transaction
PNZ	n	1	BCD	Pump & Nozzle number
				MSD (Pump number) 0 = Illegal 1 to n = Pump number (Max. 4 pump)  LSD (Nozzle number) 0 = All Nozzles Off 1 to n = Nozzle number (Max 5 nozzle)
STA	n	1	BCD	Status
				00 = IDLE (The Pump handle is OFF) 01 = CALL (The Pump handle is ON, but not authorized) 02 = BUSY (The Pump is authorized and delivering) 03 = PAUSED (Delivering paused) 04 = UNPAID (The Pump has completed a delivery with Pump handle at OFF) 05 = ERROR (The Pump is ERROR condition or communication timeout) 06 = AUTHORIZED (Pending, wait ECR authorize and/or CALL in IDLE state) 07 = WAIT (Pending, wait ECR authorize in CALL state) 08 = PAID (Pending, wait ECR paid confirmation) 09 = KYB-CALL (The Pump handle is ON, Keypad Preset data ready) 0A = INACTIVE (Inactive Mode)
AMO	n	4	BCD	Filling Amount (Included only when BUSY state)

## Command Syntax :

Valid DCR State :	All
Valid Nozzle State :	UNPAID

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	82h	1	HEX	Transaction number
LNG	1	1	HEX	Number of data bytes in the transaction
PNZ	n	1	BCD	Pump & Nozzle number
				MSD (Pump number) 0 = Illegal 1 to n = Pump number (Max. 4 pump)  LSD (Nozzle number) 0 = Illegal 1 to n = Nozzle number (Max 5 nozzle)

State after nozzle accepts the command :	IDLE
Response after POLL :	DC128

## CD131 Request End of Filling Report

## **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	UNPAID

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	83h	1	HEX	Transaction number
LNG	1	1	HEX	Number of data bytes in the transaction
PNZ	n	1	BCD	Pump & Nozzle number
				MSD (Pump number) 0 = Illegal 1 to n = Pump number (Max. 4 pump)  LSD (Nozzle number) 0 = MPD 1 to n = Nozzle number (Max 5 nozzle)

State after nozzle accepts the command :	None
Response after POLL :	DC131

# DC131 End of Filling Report

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	83h	1	HEX	Transaction number
LNG	n	1	HEX	Number of data bytes in the transaction
				If FTYP = Manual(06) : LNG=0Dh (except PLNO,FLEET,FID,RNO) else : LNG=3Bh
PNZ	n	1	BCD	Pump & Nozzle number
				MSD (Pump number)  0 = Illegal  1 to n = Pump number  (Max. 4 pump)  LSD (Nozzle number)  0 = Illegal  1 to n = Nozzle number  (Max 5 nozzle)
FTYP	n	1	BCD	Filling Type
				00 = Cash 01 = TTS 02 = MTS 03 = Barrel 04 = Transfer 05 = Test 06 = Manual 07 = Undefined 08 = Credit Card 09 = Loyalty
FAMO	n	4	BCD	Filling Amount
FVOL	n	4	BCD	Filling Volume
PPU	n	3	BCD	Price Per Unit
PLATE	n	32	ASCII	Plate Number / Customer name
FID	n	12	ASCII	Fiscal ID number
RNO	n	2	BCD	Fiscal receipt number

## CD132 Suspend / Resume

## Command Syntax :

Valid DCR State :	All
Valid Nozzle State :	BUSY

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	84h	1	HEX	Transaction number
LNG	2	1	HEX	Number of data bytes in the transaction
PNZ	n	1	BCD	Pump & Nozzle number
				MSD (Pump number)LSD (Nozzle number)0 = Illegal0 = MPD1 to n = Pump number1 to n = Nozzle number(Max. 4 pump)(Max 5 nozzle)
CMD	n	1	BCD	Command
				0 = Suspend 1 = Resume

State after nozzle accepts the command :	PAUSED / BUSY
Response after POLL :	DC128

## CD133 Request ECR Mifare Data

### **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	CALL

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	85h	1	HEX	Transaction number
LNG	01h	1	HEX	Number of data bytes in the transaction
CMD	n	1	BCD	Command
				(Command) 0 = Read 1 = Clear

State after Nozzle accepts the command :	None
Response after POLL :	DC133

## DC133 ECR Mifare Data

This transaction is sent by the DCR asynchronously at Mifare event or if the DCR receives the command "Request ECR Mifare".

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	85h	1	HEX	Transaction number
LNG	14h	1	HEX	Number of data bytes in the transaction
DATA	n	20	ASCII	Mifare Data

## CD134 Data Transfer to ECR

### **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	86h	1	HEX	Transaction number
LNG	30h	1	HEX	Number of data bytes in the transaction
SDAT	n	48	ASCII	Data block

State after nozzle accepts the command :	None
Response after POLL :	None

## DC134 Data Transfer from ECR

This transaction is sent by the DCR asynchronously when ECR Transaction "Data Transfer to SCU" arrived.

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	86h	1	HEX	Transaction number
LNG	30h	1	HEX	Number of data bytes in the transaction
EDAT	n	48	ASCII	Data block

## CD135 Request Totalizer

## **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTE	ERPRETATION
TRANS	87h	1	HEX	Transaction number	
LNG	1	1	HEX	Number of data bytes in the transaction	
PNZ	n	1	BCD	Pump & Nozzle number	
				MSD (Pump number) 0 = Illegal 1 to n = Pump number (1 to 4 : DCR Pump Totals) (5 to 8 : Real Pump Totals for Pump 1 to 4)	LSD (Nozzle number) 0 = Illegal 1 to n = Nozzle number (Max 5 nozzle)

State after nozzle accepts the command :	None
Response after POLL :	DC135

## DC135 Nozzle Totalizer

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION	
TRANS	87h	1	HEX	Transaction number	
LNG	0Fh	1	HEX	Number of data bytes in the transaction	
PNZ	n	1	BCD	Pump & Nozzle number	
				MSD (Pump number) 0 = Illegal 1 to n = Pump number 1 to n = Nozzle number (Max 5 nozzle) (1 to 4 : DCR Pump Totals) (5 to 8 : Real Pump Totals for Pump 1 to 4)	
TVOL	n	4	BCD	Volume Totalizer	
TAMO	n	6	BCD	Amount Totalizer	
QSALE	n	4	BCD	Quantity of sales	

## CD136 Authorize / Unauthorize

## Command / Response Syntax :

Valid DCR State :	All
Valid Nozzle State :	IDLE (for authorization), CALL (for unauthorization)

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION		
TRANS	88h	1	HEX	Transaction number		
LNG	n	1	HEX	Number of data bytes in the transaction		
				If ATYP = TTS or MTS : LNG=30h Else LNG =07h		
PNZ	n	1	BCD	Pump & Nozzle number		
				MSD (Pump number) 0 = Illegal 1 to n = Pump number (Max. 4 pump)  LSD (Nozzle number) 0 = MPD 1 to n = Nozzle number (Max 5 nozzle)		
PTYP	0~1	1	BCD	Preset type (0=unlimited, 1=Money, 2=Liter)		
PVAL	n	4	BCD	Preset value		
ATYP	n	1	BCD	Authorization type		
				00 = Cash 01 = TTS 02 = MTS 03 = Barrel 04 = Transfer 05 = Test 06 = Manual 07 = Unauthorize 08 = Credit Card 09 = Loyalty		
PLATE	n	8	ASCII	Plate number		
FLEET	n	32	ASCII	Customer name		
VLD	n	1	BCD	Validation		
				00 = Accepted 01 = Black List		

State after nozzle accepts the command :	CALL (for authorization), IDLE (for unauthorization)
Response after POLL :	DC128

## CD137 Request DCR Parameters

## **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	89h	1	HEX	Transaction number
LNG	1	1	HEX	Number of data bytes in the transaction
PPN	n	1	BCD	Parameter page no (0=all)

State after nozzle accepts the command :	None
Response after POLL :	None

## DC137 DCR Parameters

SYMBOL	WORDS	# BYTES	TYPE			INTER	RPRETATIO	N	
TRANS	89h	1	HEX	Transaction number					
LNG	25h	1	HEX	Number of data bytes	Number of data bytes in the transaction				
DSTA	n	1	BCD	DCR Status					
				Status Flags 7 6 5 4 3 2 1	Bit 2 : Bit 3 : Bit 4 : Bit 5 : Bit 6 :	Busy Programming N No Pump Conno Manual Sales SCU Enabled Volume Decima 48-Hours Timed Always zero	ected Il Point (1=3, 0=	2)	
RTIME	n	6	BCD	Real Date/Time (YY	MMDDhhmm	ss)			
VER	n	6	ASCII	DCR Version Numbe	er				
CTIME	n	8	ASCII	Last Compiled Date/	Time				
AUT	n	14	ASCII	Author of Code					
PRO	n	1	BCD	Selected Protocol					
				00 = Meksan/Wayne 01 = Petposan/Europ 02 = Petposan/Europ 03 = Wayne/Vista 04 = Mepsan (Unime 05 = Tokheim	oump (Beta) oump (S4)	06 = Gilbar 07 = Batch 08 = Puma 09 = Baran 10 = Maser 11 = Nouve	en Ilan Isay r	12 = Yakui 13 = CSA 14 = S&B 15 = Mites	
DTYP	n	1	BCD	Selected Dispenser	Гуре				
	1	1		00 = Typ-111 01 = Typ-122 02 = Typ-133 03 = Typ-144 04 = Typ-112 05 = Typ-113	06 = Typ- 07 = Typ- 08 = Typ- 09 = Typ- 10 = Typ- 11 = Typ-	222 244 266 288	12 = Typ-2. 13 = Typ-2. 14 = Typ-2. 15 = Typ-2. 16 = Typ-2. 17 = Typ-2.	28 12 24 36	18 = Type-248 19 = Type-2210 20 = Type-2410 21 = Undefined 22 = Undefined 23 = Undefined

## CD138 Set DCR Parameters

## Command Syntax :

Valid DCR State :	IDLE
Valid Nozzle State :	IDLE

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION			
TRANS	8Ah	1	HEX	Transaction number			
LNG	2	1	HEX	umber of data bytes in the transaction			
PPN	n	1	BCD	arameter page no (1=Fiscal Mode)			
DCRP	n	1	HEX	DCR Parameter (0=No Fiscal, 1=48 Hours, 2=Fiscal Mode)			

State after nozzle accepts the command :	None
Response after POLL :	None

## CD139 Request Sale Records

## **Command Syntax:**

Valid DCR State :	All
Valid Pump State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	8Bh	1	HEX	Transaction number
LNG	2	1	HEX	Number of data bytes in the transaction
REC	n	2	BCD	Record number (0 – 399)

State after DCR accepts the command :	None
State after Pump accepts the command :	None
Response after POLL :	DC139

## DC139 Sale Records

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	8Bh	1	HEX	Transaction number
LNG	37h	1	HEX	Number of data bytes in the transaction
PNZ	n	1	BCD	Pump & Nozzle number
				MSD (Pump number)  0 = Illegal  1 to n = Pump number  (Max. 4 pump)  LSD (Nozzle number)  0 = Illegal  1 to n = Nozzle number  (Max 5 nozzle)
RNO	n	2	BCD	Record number (circular index pointer) total 400 records
FTYP	n	1	BCD	Filling type
				01 = TTS 02 = MTS 03 = Barrel 04 = Transfer 05 = Test 06 = Manual 07 = Undefined 08 = Credit Card 09 = Loyalty
TYP	n	1	BCD	Product Type number
PPU	n	4	BCD	Filling Price Unit
VOL	n	4	BCD	Filling Volume
AMO	n	4	BCD	Filling Amount
DATE	n	3	BCD	Date (YYMMDD)
TIME	n	3	BCD	Time (HHMMSS)
PLATE	n	32	ASCII	Plate number / Customer name

## **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	8Ch	1	HEX	Transaction number
LNG	4~n	1	HEX	Number of data bytes in the transaction
PNZ	n	1	BCD	Pump & Nozzle number
				MSD (Pump number)LSD (Nozzle number)0 = Illegal0 = Illegal1 to n = Pump number1 to n = Nozzle number
				(Max. 4 pump) (Max 5 nozzle)
PPU	n	3	BCD	
PPU PNZ	n n	3	BCD BCD	(Max. 4 pump) (Max 5 nozzle)
		3 1 3	_	(Max. 4 pump) (Max 5 nozzle)  Price Per Unit
PNZ	n	1	BCD	(Max. 4 pump) (Max 5 nozzle)  Price Per Unit  Pump & Nozzle number

### >> Up to 4 Pump x 5 Nozzles

State after nozzle accepts the command :	None
Response after POLL :	None

## CD141 Request VID Status

## **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	8Dh	1	HEX	Transaction number
LNG	1	1	HEX	Number of data bytes in the transaction
RNO	n	1	BCD	Reader Number

State after nozzle accepts the command :	None
Response after POLL :	DC141

# DC141 VID Status

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	8Dh	1	HEX	Transaction number
LNG	2	1	HEX	Number of data bytes in the transaction
RNO	n	1	BCD	Reader Number
VSTA	n	1	BCD	VID Status
				00 = No VID 01 = Legal VID 02 = Illegal VID

## CD142 Request VID Data

# Command Syntax :

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	8Eh	1	HEX	Transaction number
LNG	1	1	HEX	Number of data bytes in the transaction
RNO	n	1	BCD	Reader Number

State after nozzle accepts the command :	None
Response after POLL :	DC142

## DC142 VID Data

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	8Eh	1	HEX	Transaction number
LNG	4Ah	1	HEX	Number of data bytes in the transaction
RNO	n	1	BCD	Reader Number
VSTA	n	1	BCD	VID Status
				00 = No VID 01 = Legal VID 02 = Illegal VID
VID	n	8	BCD	VID Identity
VDAT	n	64	ASCII	VID Data

## CD143 Request CID Status

## **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	8Fh	1	HEX	Transaction number
LNG	1	1	HEX	Number of data bytes in the transaction
RNO	n	1	BCD	Reader Number

State after nozzle accepts the command :	None
Response after POLL :	DC143

## DC143 CID Status

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	8Fh	1	HEX	Transaction number
LNG	2	1	HEX	Number of data bytes in the transaction
RNO	n	1	BCD	Reader Number
CSTA	n	1	BCD	CID Status
				00 = No CID 01 = Legal CID 02 = Illegal CID

## CD144 Request CID Data

## Command Syntax :

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	90h	1	HEX	Transaction number
LNG	1	1	HEX	Number of data bytes in the transaction
RNO	n	1	BCD	Reader Number

State after nozzle accepts the command :	None
Response after POLL :	DC144

## DC144 CID Data

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	90h	1	HEX	Transaction number
LNG	4Ah	1	HEX	Number of data bytes in the transaction
RNO	n	1	BCD	Reader number
CSTA	n	1	BCD	CID Status
				00 = No CID 01 = Legal CID 02 = Illegal CID
CID	n	8	BCD	CID Identity
CDAT	n	64	ASCII	CID Data

# CD145 Update Info Display

## Command Syntax :

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	91h	1	HEX	Transaction number
LNG	1Bh	1	HEX	Number of data bytes in the transaction
BUZ	n	1	BCD	Buzzer (0=off, nn=beep duration)
DNO	n	1	BCD	Display number
LNO	n	1	BCD	Line number
DDAT	n	24	ASCII	Display data

State after nozzle accepts the command :	None
Response after POLL :	None



# CD146 Read Keypad Buffer

## **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	92h	1	HEX	Transaction number
LNG	1	1	HEX	Number of data bytes in the transaction
KNO	n	1	BCD	Keypad number

State after nozzle accepts the command :	None
Response after POLL :	DC146

## DC146 Keypad Buffer

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	92h	1	HEX	Transaction number
LNG	21h	1	HEX	Number of data bytes in the transaction
KNO	n	1	BCD	Keypad number
KDAT	n	32	ASCII	Keypad data

## CD147 Request Error Report

## **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	93h	1	HEX	Transaction number
LNG	1	1	HEX	Number of data bytes in the transaction
DEV	n	1	BCD	Device number
				00 = DCR 01 = Pump 1 02 = Pump 2 03 = Pump 3 04 = Pump 4 05 = ECR

State after nozzle accepts the command :	None
Response after POLL :	DC147

## DC147 Error Event Report

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	93h	1	HEX	Transaction number
LNG	2	1	HEX	Number of data bytes in the transaction
DEV	n	1	BCD	Device number
				00 = DCR 01 = Pump 1 02 = Pump 2 03 = Pump 3 04 = Pump 4 05 = ECR
ECODE	n	1	BCD	Error Code

## CD148 Request DCR Status

## **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	94h	1	HEX	Transaction number
LNG	2	1	HEX	Number of data bytes in the transaction
DCR	n	1	BCD	DCR number
TMO	n	1	BCD	SCU Timeout (099) 10 to 1000 seconds.

State after nozzle accepts the command :	None
Response after POLL :	DC148

## DC148 DCR Status

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	94h	1	HEX	Transaction number
LNG	0Ch	1	HEX	Number of data bytes in the transaction
DCR	n	1	BCD	DCR number
STA	n	1	BCD	DCR Status
				00 = IDLE 01 = Manual Mode 02 = ECR Mode
SER	n	4	HEX	DCR Serial Number
FMOD	n	1	BCD	Fiscal Mode (00=No Fiscal, 01=48-Hours, 02=Fiscal)
VER	n	3	BCD	DCR Version
CRC16	n	2	HEX	DCR Firmware CRC16

WOT IMPLEMENTED.

# CD150 Pump Bypass Mode

## **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	Idle

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	96h	1	HEX	Transaction number
LNG	n	1	HEX	Number of data bytes in the transaction
Pass	n	4	BCD	Password
Mode	n	1	BCD	01=Entry, 00=Exit
Size	n	1	HEX	Command Set size
CMD	n	n	any	Command Set (Max.64-Byte) * Real Pump protocol string

Response Syntax: From Pump (Real Pump Protocol String.)

## CD151 Request ECR Plate

### **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	97h	1	HEX	Transaction number
LNG	1	1	HEX	Number of data bytes in the transaction
PNZ	n	1	BCD	Pump & Nozzle number
				MSD (Pump number) 0 = Illegal 1 to n = Pump number (Max. 4 pump)  LSD (Nozzle number) 0 = MPD 1 to n = Nozzle number (Max 5 nozzle)

State after nozzle accepts the command :	None
Response after POLL :	DC151

## DC151 ECR Plate

This transaction is sent by the DCR asynchronously when ECR Transaction "Authorize / Unauthorize" arrived. (if ECR+ protocol selected)

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	97h	1	HEX	Transaction number
LNG	21h	1	HEX	Number of data bytes in the transaction
PNZ	n	1	BCD	Pump & Nozzle number
				MSD (Pump number)LSD (Nozzle number)0 = Illegal0 = MPD1 to n = Pump number1 to n = Nozzle number(Max. 4 pump)(Max 5 nozzle)
PLATE	n	32	ASCII	Plate Number / Customer name

## CD152 Slip Data to ECR

## **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	98h	1	HEX	Transaction number
LNG	25h	1	HEX	Number of data bytes in the transaction
PMP	n	1	BCD	Pump Number (1-4)
TYP	n	1	BCD	Slip Type (0=Loyalty, 1=POS, 2=Info)
TLINE	n	1	HEX	Total Line Number (1 to 64 line)
CHR	n	1	BCD	Character Type of Line (0=Normal, 1=Bold)
LINE	n	1	HEX	Line number (1 to 64 line)
INFO	n	32	ASCII	Data block

State after nozzle accepts the command :	None
Response after POLL :	None

# DC152 Request Slip Data

This transaction is sent by the DCR Asynchronously.

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	98h	1	HEX	Transaction number
LNG	03h	1	HEX	Number of data bytes in the transaction
PMP	n	1	BCD	Pump Number (1-4)
TYP	n	1	BCD	Slip Type (0=Loyalty, 1=POS, 2=Info)
LN	n	1	HEX	Request Line number

## CD153 Request Unit Price

### **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	99h	1	HEX	Transaction number
LNG	01h	1	HEX	Number of data bytes in the transaction
PMP	n	1	BCD	Pump Number (1~4)

State after DCR accepts the command :	None
State after Pump accepts the command :	None
Response after POLL :	DC153

## DC153 Unit Price

This transaction is sent by the DCR asynchronously at change of a value or if the DCR receives the command "Request Unit Price".

### **Command Syntax:**

Valid DCR State :	All
Valid Pump State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	99h	1	HEX	Transaction number
LNG	10h	1	HEX	Number of data bytes in the transaction
PMP	n	1	BCD	Pump number (1~4)
PRI1	n	3	BCD	Price for Nozzle-1
PRI2	n	3	BCD	Price for Nozzle-2
PRI3	n	3	BCD	Price for Nozzle-3
PRI4	n	3	BCD	Price for Nozzle-4
PRI5	n	3	BCD	Price for Nozzle-5

Data is sent in packed BCD with MSB in first byte.



## CD154 DCR Reset

## **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION	
TRANS	9Ah	1	HEX	Fransaction number	
LNG	01h	1	HEX	umber of data bytes in the transaction	
RST	n	1	BCD	= Software Reset, 1 = Hardware Reset	

State after DCR accepts the command :	None
State after Pump accepts the command :	None
Response after POLL :	None

## CD155 Update DCR Date/Time

## Command Syntax :

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION	
TRANS	9Bh	1	HEX	Transaction number	
LNG	06h	1	HEX	Number of data bytes in the transaction	
DATE	n	3	BCD	Date (YYMMDD)	
TIME	n	3	BCD	ime (HHMMSS)	

State after DCR accepts the command :	None
State after Pump accepts the command :	None
Response after POLL :	None

## CD156 Request Keypad Status

### **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION	
TRANS	9Ch	1	HEX	Fransaction number	
LNG	1	1	HEX	lumber of data bytes in the transaction	
PNO	n	1	BCD	Pump Number (1~4)	

State after nozzle accepts the command :	None
Response after POLL :	DC156

## DC156 Keypad Status

This transaction is sent by the DCR asynchronously when status changed.

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION	
TRANS	9Ch	1	HEX	Transaction number	
LNG	18h	1	HEX	Number of data bytes in the transaction	
PNO	n	1	BCD	Pump Number (1~4)	
PTYP	0~2	1	BCD	Preset type (0=unlimited, 1=Money, 2=Liter)	
PVAL	n	4	BCD	Preset value	
PAYM	n	1	BCD	Payment type (1=Cash, 2=Credit, 3=Custom)	
TAGT	n	1	BCD	TAG Type	
			00 = No Tag 01 = Mifare Ultralight 02 = Mifare Standard 1K 03 = Mifare Classic 4K 0xFF = Unknown Tag Type		
PTAG	n	8	HEX	Pumper Card Serial	
CTAG	n	8	HEX	Customer Card Serial	

## CD157 Request Shift Totalizer

## **Command Syntax:**

Valid DCR State :	All
Valid Nozzle State :	All

SYMBOL	WORDS	# BYTES	TYPE	INTER	RPRETATION
TRANS	9Dh	1	HEX	Transaction number	
LNG	2	1	HEX	Number of data bytes in the transaction	
PNZ	n	1	BCD	Pump & Nozzle number	
				MSD (Pump number) 0 = Illegal 1 to n = Pump number	LSD (Nozzle number) 0 = Illegal 1 to n = Nozzle number (Max 5 nozzle)
SHF	1	1	HEX	0=Read Shift Totals, 1=Set Shifts Totals	

State after nozzle accepts the command :	None
Response after POLL :	DC157

## DC157 Shift Totalizer

SYMBOL	WORDS	# BYTES	TYPE	INTERPRETATION
TRANS	9Dh	1	HEX	Transaction number
LNG	25h	1	HEX	Number of data bytes in the transaction
PNZ	n	1	BCD	Pump & Nozzle number
				MSD (Pump number)LSD (Nozzle number)0 = Illegal0 = Illegal1 to n = Pump number1 to n = Nozzle number (Max 5 nozzle)
DATE	n	3	BCD	Shift Date (YYMMDD)
TIME	n	3	BCD	Shift Time (HHMMSS)
CVOL	n	4	BCD	Current Volume Totalizer
CAMO	n	6	BCD	Current Amount Totalizer
SVOL	n	4	BCD	Shift Volume Totalizer
SAMO	n	6	BCD	Shift Amount Totalizer
DVOL	n	4	BCD	DCR Volume Totalizer
DAMO	n	6	BCD	DCR Amount Totalizer